


## SAMS DOMESTIC: GETTING STARTED

- **Launch** the Google Chrome web browser
- **Type** in the URL (<http://winauth.com/download>)

## SETTING UP THE AUTHENTICATOR

- Multifactor Authentication (MFA) is an extra layer of security designed to help authenticate a user's identity before entering the **SAMS Domestic Portal**




**1. Click on the link for the latest stable version of WinAuth to download it.**


WinAuth 3.5.1 (2016-06-07)  
MD5: 9393C999D1412C0D28CCCEA0F9CB95C3. WinAuth

(Windows 7 / 8.x / 10 requires **Microsoft .NET Framework 4.5**)


Users of Windows 7, 8, or 10 may first need to download Microsoft .NET Frame 4.5 before proceeding with downloading **WinAuth**.




**2. Click on the WinAuth-3.5.1.zip folder that appears on the downloads bar.**



**3. In the folder that opens, double click on the WinAuth.exe file.**



**4. Click the Add button in the main WinAuth window.**




**5. Select Authenticator from the dropdown menu.**

**6. In the Name field, type "SAMS Domestic MFA".**


**Do NOT close the WinAuth window at this time.**

## ENABLING MULTI-FACTOR AUTHENTICATION

- **Open** a new Google Chrome window
- **Type** in the URL (<https://mygrants.service-now.com/>)




**7. Log in to the SAMS Domestic Portal.**



**8. On the Enable multi-factor authentication page, copy the unique secret code.**

2JPS LWMG L12P MHAF

**9. Paste the secret code copied from the SAMS Domestic Enable multi-factor authentication page into the secret code field.**



**10. Ensure that Time-based is selected.**

**11. Click Verify Authenticator.** A one-time, six-digit authentication code will generate.


122505

**12. Within 30 seconds, return to the SAMS Domestic Enable multi-factor authentication page. Type the authentication code, without spaces, into the authentication code field and click Pair device and Login.**


Each **authentication code** is valid only for 30 seconds. A new code will be generated automatically. The **green timer** bar shows the remaining time.

## ENABLING MULTI-FACTOR AUTHENTICATION


- Return to the WinAuth window



- WinAuth** should now be set up to generate authentication codes for **SAMS Domestic** log in




- Move the **WinAuth** program file to an easily accessible location




## USING WINAUTH FOR MFA LOG IN


- MFA is required every time a user logs into the **SAMS Domestic Portal**
- Launch Google Chrome
- Type in the URL (<https://mygrants.service-now.com/>)



- Open **WinAuth**
- If a **WinAuth** password was created during *Completing Authentication Setup*, enter it now



- Return to the **SAMS Domestic 2-Factor Authentication** page



## GETTING HELP

- Contact the ILMS Support Desk at 1-888-313-ILMS (4567) or via **Self Service Portal** at <https://afsitsm.service-now.com/ilms/home>
- Access additional training resources on the **SAMS Domestic Portal Support** page at <http://mygrants.service-now.com>